

## Mergene1000<sup>®</sup> THP-1 Cell-Specific mRNA Transfection Reagent

Cat. No. : 164435

Size: 100 $\mu$ L / 0.5mL / 1mL


### General Information

Product From	Liquid
Product Color	Colorless
Product Packaging	1 tube
Storage	2-8 $^{\circ}$ C <sup>®</sup>
Expiration Date	18 months
Shipping	Ice bag

### Background

Mergene1000<sup>®</sup> THP-1 Cell-Specific mRNA Transfection Reagent is a high-performance mRNA transfection reagent designed for the delivery of mRNA. It can directly deliver mRNA into the cytoplasm for expression, thereby avoiding the limitations of transcriptional regulation and entry into the nucleus. It is specifically formulated for use with THP-1 cells, achieving high transfection efficiency. The reagent is distinguished by its low toxicity, excellent stability, ease of operation, and high reproducibility.

### Product Operation Flowchart



### Usage Steps

To transfect THP-1 cells, follow the steps outlined below. Using 24-well plates as an example, mix Mergene1000<sup>®</sup> THP-1 Cell-Specific mRNA Transfection Reagent ( $\mu$ L) with mRNA ( $\mu$ g) at a ratio of 5:1. This ratio can be adjusted between 3:1 and 7:1 according to the situation. For other sizes of culture plates or dishes, refer to the recommended transfection amounts provided in Table 1.

#### 1. Cell seeding

Before transfection, ensure that the cells are healthy and cell viability exceeding 90%. Add 500  $\mu$ L RPMI-1640 (PM150110) + 10% FBS + 0.05 mM  $\beta$ -mercaptoethanol + 1% P/S (PB180120) medium to each well, and start transfection when the final cell density reaches  $4-8 \times 10^5$  cells/mL/well.

#### 2. Preparation of the transfection complex

- (1) Prepare a sterile centrifuge tube, add 50  $\mu\text{L}$  RPMI-1640 medium (PM150110), and then add 1.0  $\mu\text{L}$  of Mergene1000<sup>®</sup> THP-1 Cell-Specific mRNA Transfection Reagent to the tube containing the medium, and gently blow and mix. Then add 0.2  $\mu\text{g}$  mRNA to the above transfection reagent dilution solution and blow and mix.

**Note:** The above is the amount of preparation for each well of cells. Please calculate the required volumes based on your specific experimental conditions and requirements.

- (2) Allow the above dilution to incubate at room temperature for 5 to 10 minutes.

### 3. Cell transfection

- (1) Add the prepared transfection complex dropwise to the cells and mixed, incubated at 37°C with 5% CO<sub>2</sub> for culture.
- (2) After 12-24 hours of incubation, detect gene expression.

**Table 1. Reference dosage of THP-1 cells transfection in different culture vessel**

Culture Vessel	Area	Cell Density Before Transfection	Inoculation Medium	Diluted Final Volume	mRNA Transfection	
					Reagent Amount	mRNA Amount
96-well	0.3 cm <sup>2</sup>	1-4×10 <sup>4</sup> cells/mL/well	200 $\mu\text{L}$	10 $\mu\text{L}$	0.5 $\mu\text{L}$	0.1 $\mu\text{g}$
24-well	2.0 cm <sup>2</sup>	4-8×10 <sup>5</sup> cells/mL/well	500 $\mu\text{L}$	50 $\mu\text{L}$	1.0 $\mu\text{L}$	0.2 $\mu\text{g}$
12-well	4.0 cm <sup>2</sup>	0.8-1.6×10 <sup>6</sup> cells/mL/well	1 mL	100 $\mu\text{L}$	2.0 $\mu\text{L}$	0.4 $\mu\text{g}$
6-well	10.0 cm <sup>2</sup>	2-4×10 <sup>6</sup> cells/mL/well	2 mL	200 $\mu\text{L}$	5.0 $\mu\text{L}$	1.0 $\mu\text{g}$
6 cm	20.0 cm <sup>2</sup>	4-8×10 <sup>6</sup> cells/mL/well	5 mL	0.5 mL	10.0 $\mu\text{L}$	2.0 $\mu\text{g}$
10 cm	60.0 cm <sup>2</sup>	1.2-2.4×10 <sup>7</sup> cells/mL/well	15 mL	1.0 mL	30.0 $\mu\text{L}$	6.0 $\mu\text{g}$

**Note:** The usage amounts provided in the table are for reference only. The exact amount of mRNA used with Mergene1000<sup>®</sup> THP-1 Cell-Specific mRNA Transfection Reagent should be optimized according to the cell conditions and other experimental parameters.

### Notes

1. This product is only used for scientific research or further research, not for diagnosis and treatment.
2. The cell inoculation amount and transfection ratio provided above are based on experiments conducted with THP-1 cells and are for reference only. The specific experimental dosage should be adjusted according to the actual conditions.
3. The product is transported with ice bag and can be aliquoted and stored upon use to avoid multiple prolonged openings of the lid.
4. RPMI-1640 medium should be prepared separately for the dilution of mRNA and transfection reagents.
5. After transfection, there is no need to remove the transfection complex or replace with fresh culture medium. The actual operation can be based on the cell status, after transfection culture 4-6 hours to choose to add the medium.
6. The use of high purity mRNA is helpful to obtain higher transfection efficiency.
7. The experimental process utilized RNA-free and pyrogen-free materials, such as centrifuge tubes, pipette tips, and buffers.

- For your safety and health, please wear experimental clothes and wear disposable gloves aseptic operation.

### Experimental Results Show (For reference only)




Figure 1. Bright-field and fluorescence images of THP-1 cells transfected with EGFP-mRNA using Mergene1000<sup>®</sup> THP-1 Cell-Specific mRNA Transfection Reagent.




Figure 2. Transfection efficiency of THP-1 cells transfected with EGFP-mRNA using Mergene1000<sup>®</sup> THP-1 Cell-Specific mRNA Transfection Reagent.